



#### Intrusion Detection Evaluation

# Prof. Ravi Sandhu Executive Director and Endowed Chair

Lecture 12

ravi.utsa@gmail.com www.profsandhu.com



## **IDS** Categorization



Property	IDS Type				
Monitored platform	Host based				
	Network based				
	Hybrid				
Attack detection method	Misuse based				
	Anomaly based				

	Hybrid
Deployment architecture	Nondistributed
	Distributed



## **IDS** Categorization



Property	IDS Type	
Monitored platform	Host based	
	Network based	
	Hybrid	
Attack detection method	Misuse based	<b>—</b>
	Anomaly based	
	Hybrid	,
Deployment architecture	Nondistributed	
architecture	Distributed	



## Design Space




- Workloads
- Metrics
- Measurement methodology



### Workloads








### Workloads








## Vulnerability and Attack Injection







### Honeypots




Production systems Pure Sebek (http://projects.honeynet.org/sebek) Argos (http://www.few.vu.nl/argos/) Capture-HPC (https://projects.honeynet.org/capture-hpc/wiki) HoneyClient (http://www.honeyclient.org/) High interaction honeybrid (http://honeybrid.sourceforge.net/) Hybrid HoneySpider (http://www.honeyspider.net/) honeyd (http://www.honeyd.org/) nepenthes (http://nepenthes.carnivore.it/) honeytrap (http://honeytrap.carnivore.it/) HoneyC (https://projects.honeynet.org/honeyc) Low interaction Level of interaction

Fig. 3. Honeypots of different levels of interaction.



### Metrics







### Metrics: Basic




(A)	False-negative rate	$\beta = P(\neg A I)$
	True-positive rate	$1 - \beta = 1 - P(\neg A I) = P(A I)$
Pagia	False-positive rate	$\alpha = P(A \neg I)$
Basic	True-negative rate	$1 - \alpha = 1 - P(A \neg I) = P(\neg A \neg I)$
Dependent on	Positive predictive value	$P(I A) = \frac{P(I)P(A I)}{P(I)P(A I) + P(\neg I)P(A \neg I)}$
base rate	Negative predictive value	$P(\neg I   \neg A) = \frac{P(\neg I)P(\neg A   \neg I)}{P(\neg I)P(\neg A   \neg I) + P(I)P(\neg A   I)}$



### Receiver Operating Curve (ROC)








### Zero Reference Curve (ZRC)







### **ROC** Limitations



- Intrusion detection is not a binary yes/no problem
- Unit of measurement is ambiguous
  - Flow versus packet
- Does not account for base rate P(I)



### Receiver Operating Curve (ROC)






Fig. 2. ROC-curves for the "low performers".




Fig. 3. ROC-curve for the "high performers".

Assumed ROC: fixes 1 point, 0.7 Detection rate, 0.00001 False alarm rate Others are reported results from literature
All anomaly detectors are in Fig 2

Axelsson, Stefan. The base-rate fallacy and the difficulty of intrusion detection. ACM Transactions on Information and System Security (TISSEC) 3, no. 3 (2000): 186-205. Figures 2 and 3



#### Intrusion Detection Effectiveness



Table VII. Values of  $1 - \beta$ ,  $PPV_{ID}$ ,  $C_{exp}$ ,  $C_{rec}$ , and  $C_{ID}$  for  $IDS_1$  and  $IDS_2$ 

-			$\mathrm{IDS}_1$			$\mathrm{IDS}_2$			
$\alpha$	$PPV_{ZRC}$	$1-\beta$	$PPV_{ID}$	$C_{exp/rec}$	$C_{ID}$	$1-\beta$	$PPV_{ID}$	$C_{exp/rec}$	$C_{ID}$
0.005	0,9569	0.9885	0,9565	0.016	0.9159	0.973	0,9558	0.032	0.8867
0.010	0,9174	0.99	0,9167	0.019	0.8807	0.99047	0,9167	0.019	0.8817
0.015	0,8811	0.9909	0,8801	0.022	0.8509	0.99664	0,8807	0.017	0.8635




Fig. 5. IDS comparison with ROC curves (a) and the intrusion detection effectiveness metric (b, c).



#### Intrusion Detection Effectiveness



Table VII. Values of  $1 - \beta$ ,  $PPV_{ID}$ ,  $C_{exp}$ ,  $C_{rec}$ , and  $C_{ID}$  for  $IDS_1$  and  $IDS_2$ 

-			$\mathrm{IDS}_1$			${ m IDS}_2$			
$\alpha$	$PPV_{ZRC}$	$1-\beta$	$PPV_{ID}$	$C_{exp/rec}$	$C_{ID}$	$1-\beta$	$PPV_{ID}$	$C_{exp/rec}$	$C_{ID}$
0.005	0,9569	0.9885	0,9565	0.016	0.9159	0.973	0,9558	0.032	0.8867
0.010	0,9174	0.99	0,9167	0.019	0.8807	0.99047	0,9167	0.019	0.8817
0.015	0,8811	0.9909	0,8801	0.022	0.8509	0.99664	0,8807	0.017	0.8635




Fig. 5. IDS comparison with ROC curves (a) and the intrusion detection effectiveness metric (b, c).



#### Intrusion Detection Effectiveness



Assumes Base rate, P(I) = 0.1

Table VII. Values of  $1 - \beta$ ,  $PPV_{ID}$ ,  $C_{exp}$ ,  $C_{rec}$ , and  $C_{ID}$  for  $IDS_1$  and  $IDS_2$ 

-			${ m IDS}_1$			$\mathrm{IDS}_2$			
$\alpha$	$PPV_{ZRC}$	$1-\beta$	$PPV_{ID}$	$C_{exp/rec}$	$C_{ID}$	$1-\beta$	$PPV_{ID}$	$C_{exp/rec}$	$C_{ID}$
0.005	0,9569	0.9885	0,9565	0.016	0.9159	0.973	0,9558	0.032	0.8867
0.010	0,9174	0.99	0,9167	0.019	0.8807	0.99047	0,9167	0.019	0.8817
0.015	0,8811	0.9909	0,8801	0.022	0.8509	0.99664	0,8807	0.017	0.8635




Fig. 5. IDS comparison with ROC curves (a) and the intrusion detection effectiveness metric (b, c).

T<sub>FP</sub>: max acceptable false positive rate Compare area difference between PPV<sub>ZRC</sub> and PPV<sub>IDS</sub> up to T<sub>FP</sub>



### Metrics: Cost-Based



## These $p_1$ $p_2$ $p_3$ are different, apply to false alert filter


 $C_{\alpha}$ : cost of false positive  $C_{\beta}$ : cost of false negative

$$C = C_{\beta}/C_{\alpha}$$

$$p_1 = P(A)$$

$$p_2 = P(I|A)$$

$$p_3 = P(I|\neg A)$$






Fig. 6. Decision tree for calculating expected cost (a) and relative expected cost (b).

$$C_{exp} = Min(C\beta B, (1-\alpha)(1-B)) + Min(C(1-\beta)B, \alpha(1-B))$$

$$C_{rec} = C\beta B + \alpha(1-B)$$



### **Metrics: Cost-Based**



Table VII. Values of  $1 - \beta$ ,  $PPV_{ID}$ ,  $C_{exp}$ ,  $C_{rec}$ , and  $C_{ID}$  for  $IDS_1$  and  $IDS_2$ 


			$\mathrm{IDS}_1$			${ m IDS}_2$			
$\alpha$	$PPV_{ZRC}$	$1-\beta$	$PPV_{ID}$	$C_{exp/rec}$	$C_{ID}$	$1-\beta$	$PPV_{ID}$	$C_{exp/rec}$	$C_{ID}$
0.005	0,9569	0.9885	0,9565	0.016	0.2159	0.973	0,9558	0.032	0.8867
0.010	0,9174	0.99	0,9167	0.019	0.8807	0.99047	0,9167	0.019	0.8817
0.015	0,8811	0.9909	0,8801	0.022	0.8509	0.99664	0,8807	0.017	0.8635

#### Assumptions:

B = 0.1

C = 10

 $\alpha$ ,  $\beta$  same for base IDS and its false alarm filter






Fig. 7. IDS comparison with the expected cost and relative expected cost metric (a) and the intrusion detection capability metric (b).



## Measurement Methodology



Table VIII. IDS Evaluation Design Space: Measurement Methodology

	Workloads	Metri	Metrics			
IDS Property	[Content]	[Aspect]	[Form]			
	Attack Detection Rela	ated				
Attack detection accuracy	Mixed	Security related	Basic, composite			
Attack coverage	Pure malicious	Security related	Basic			
Resistance to evasion techniques	Pure malicious, mixed	Security related	Basic			
Attack detection and reporting speed	Mixed	Performance related	n/a			
	esource Consumption I	Related				
CPU consumption	Pure benign	Performance related	n/a			
Memory consumption						
Network consumption						
Performance overhead	Pure benign	Performance related	n/a			
Workload processing capacity	Pure benign	Performance related	n/a			
]	Definitions of IDS Prop	perties				
IDS Property		Definition				
Attack detection accuracy	The attack detection workloads.	accuracy of an IDS in the	e presence of mixed			
Attack coverage		n accuracy of an IDS in the background benign activi				
Performance overhead	The overhead incurred by an IDS on the system and/or network environment where it is deployed. Under overhead, we understand performance degradation of users' tasks/operations caused by (a) consumption of system resources (e.g., CPU, memory) by the IDS and/or (b) interception and analysis of the workloads of users' tasks/operations (e.g., network packets) by the IDS.					
Workload processing capacity	The rate of arrival of workloads to an IDS for processing in relation to the amount of workloads that the IDS discards (i.e., does not manage to process). For instance, in the context of network-based IDSes, capacity is normally measured as the rate of arrival of network packets to an IDS over time in relation to the amount of discarded packets over time. The capacity of an IDS may also be defined as the maximum workload processing rate of the IDS such that there are no discarded workloads.					



## Case Study: Snort



Table X. Attack Coverage of Snort

Targeted Vulnerability (CVE ID)	Platform	Detected
CVE-2011-3192	Apache	X
CVE-2010-1870	<b>Apache Struts</b>	$\checkmark$
CVE-2012-0391	Apache Struts	X
CVE-2013-2251	Apache Struts	X
CVE-2013-2115/CVE-2013-1966	<b>Apache Struts</b>	✓
CVE-2009-0580	Apache Tomcat	X
CVE-2009-3843	<b>Apache Tomcat</b>	X
CVE-2010-2227	Apache Tomcat	X

✓, detected; x, not detected.

Table XI. Resistance to Evasion Techniques of Snort

Evasion Technique	Targeted Vulnerability (CVE ID)				
	CVE-2010-1870	CVE-2013-2115/CVE-2013-1966			
HTTP::uri_use_backslashes	✓	✓			
HTTP::uri_fake_end	✓	✓			
HTTP::pad_get_params	✓	x			
HTTP::uri_fake_params_start	✓	✓			
HTTP::uri_encode_mode (u-random; hex-random)	✓	X			
HTTP::pad_method_uri_count	✓	✓			
HTTP::method_random_valid	✓	x			
HTTP::header_folding	✓	✓			
HTTP::uri_full_url	✓	✓			
HTTP::pad_post_params	✓	X			
HTTP::uri_dir_fake_relative	✓	✓			
HTTP::pad_uri_version_type (apache; tab)	✓	✓			
HTTP::uri_dir_self_reference	✓	✓			
HTTP::method_random_case	<b>√</b>	✓			

<sup>✓,</sup> detected; x, not detected.

True positive rate = 2/8 = 0.25

True positive rate = 24/28 = 0.85




## Case Study: Snort



Table XII. Attack Detection Accuracy of Snort: Basic Metrics (seconds=120)

Configuration	Metrics					
	α	$1-\beta$	PPV	NPV		
count=6	0.0008	0.333	0.9788	0.9310		
count=5	0.0011	0.416	0.9768	0.9390		
count=4	0.0013	0.5	0.9771	0.9473		
count=3	0.0017	0.624	0.9761	0.9598		
count=2	0.0024	0.833	0.9747	0.9817		
Default configuration	0.0026	0.958	0.9762	0.9953		







Fig. 8. Attack detection accuracy of Snort: composite metrics. ROC curve and estimated costs (a) and  $C_{ID}$  curve (b) ( $\square$  marks an optimal operating point).



## Case Study: Snort








Fig. 9. CPU consumption of Snort (a) and packet drop rate of Snort (b) ( $\square$  marks the data point whose x value is the network traffic speed that corresponds to the maximum workload processing rate of Snort such that there are no discarded workloads).



## Measurement Methodology



Table XIII. Summarizing Overview of Common Trends, Recommendations, and Key Best Practices

IDS Property	
Attack detection accuracy Attack coverage	These properties are evaluated for IDSes of all types. • The dated DARPA and KDD-99 Cup datasets represent at this time standard workloads for comparing novel anomaly-based IDSes with their past counterparts. • For the sake of representativeness, evaluate an IDS using not the DARPA or the KDD-99 Cup dataset but workloads that contain current attacks. • Attack detection rates of current IDSes vary greatly—that is, between 8% and 97%, measures that depend on the configurations of the tested IDSes and the applied evaluation methodologies.
Attack detection and reporting speed	This property is normally evaluated for distributed IDSes—it is best evaluated by measuring the time needed for the IDS to converge to a state in which all of its nodes, or the designated nodes, are notified of an ongoing attack. • Attack detection delays up to 3 seconds are considered acceptable.
Resistance to evasion techniques	This property is often not evaluated, as it is considered of limited practical importance. • Consider evaluating this property since a single successful IDS evasion attack poses the danger of a high-impact intrusion. • Metasploit is deemed the optimal tool for executing IDS evasive attacks, which is required for evaluating this property. • Many current IDSes are vulnerable to temporally crafted attacks.
Resource consumption related	These properties are typically evaluated for IDSes deployed in resource-constrained environments. • Network consumption in particular is often evaluated for distributed IDSes. • The resource consumption of a distributed IDS operating in wireless ad hoc networks is typically evaluated to measure the power consumption of its nodes—this is best performed by using a model that estimates power consumption based on resource consumption measurements.
Performance overhead	This property is normally evaluated for host-based IDSes. • Performance overhead is evaluated by executing tasks twice, once with the tested IDS being inactive and once with it being active. • This property is normally evaluated using workloads in executable form generated by workload drivers—workload drivers enable the straightforward generation of live customized workloads in a repeatable manner. • Overheads under 10%, relative to the execution time of tasks measured when the tested IDS is inactive, are generally considered acceptable.
Workload processing capacity	This property is normally evaluated for network-based IDSes that monitor high-rate workloads. • This property is best evaluated using traces or workload drivers, as they allow for the generation of workloads at user-defined speeds. • Evaluate the capacity of an IDS together with its resource consumption—this enables one to observe how resource consumption scales as workload intensity increases.



## **Future Directions**



- High speed IDSs
- IDSs for virtualized environments (e.g., cloud)
- IDSs for detecting APTs (advanced persistent threats)
- IDSs for detecting zero day attacks